

# SONY



# Vision and Sensing Application SDK Model Quantization Functional Specifications

Copyright 2023 Sony Semiconductor Solutions Corporation

Version 0.2.0

2023 - 1 - 30

AITRIOS™ and AITRIOS logos are the registered trademarks or trademarks  
of Sony Group Corporation or its affiliated companies.

# TOC

1. Change history	1
2. Terms/Abbreviations	2
3. Reference materials	3
4. Expected use case	4
5. Functional overview/Algorithm	5
6. User interface specifications	8
7. Target performances/Impact on performances	15
8. Assumption/Restriction	16
9. Remarks	17
10. Unconfirmed items	18

# 1. Change history

Date	What/Why
2022/11/16	Initial draft
2023/01/30	<p>Fixed how images are stored for quantization calibration and evaluation.</p> <p>Added how to store the label information file used during evaluation.</p> <p>Removed the <code>evaluate_ground_truth_file</code> setting and added the <code>evaluate_label_file</code> setting.</p> <p>Fixed the default path for the <code>dataset_image_dir</code>, <code>evaluate_image_dir</code> settings.</p> <p>Added supported image formats.</p> <p>Directory structure change.</p> <p>Added that symbolic links must not be used.</p> <p>Following the deletion of the secret information, Initial was removed from the configuration file entry and added about creating a configuration file.</p> <p>Updated the PDF build environment.</p>

## 2. Terms/Abbreviations

Terms/Abbreviations	Meaning
<a href="#">MCT</a>	Open source software for quantizing neural network models
Keras	A Keras model is a type of neural network format
TFLite	TensorFlow Lite A <i>.tflite</i> model is a type of neural network format
Iteration	One occasion of neural network model training

## 3. Reference materials

- Reference/Related documents
  - Model Compression Toolkit (MCT)
    - [https://github.com/sony/model\\_optimization](https://github.com/sony/model_optimization)

## 4. Expected use case

- You want to quantize the model


You want to reduce the size of the model by quantization so that it can be deployed to the target edge AI device

- You want to run inferences and confirm accuracy using pre- and post-quantization models


# 5. Functional overview/Algorithm

## Functional overview

- The SDK quantizes the AI model (Keras) of image classification and converts it to an AI model (TFLite) in the following flow
- The SDK runs inferences on pre- and post-quantization AI models to get statistics (Top1 accuracy) for the inference results
- The AI models supported by the SDK conform to [MCT supported features](#)
- The image format supported by the SDK is JPEG



- Flow overview





- Flow details

1. Prepare an AI model to quantize

- Prepare an AI model (Keras) to quantize

2. Prepare images for quantization and evaluation

- Prepare images used in training AI models because they will be used to calibrate the quantization
- Prepare images and their label information for validation of AI models because they will be used as input during inference evaluation

3. Create and edit the configuration file for quantization

- Create and edit the configuration file [configuration.json](#) to configure notebook runtime settings

4. Edit the notebook

- Modify the implementation of the preprocessing part for calibration in the notebook according to the AI model used

5. Run quantization and evaluation

- Run the notebook that quantizes an AI model (Keras), converts it to an AI model (TFLite), and evaluates inferences

# 6. User interface specifications

## How to start each function

1. Launch the SDK environment and preview the **README.md** in the top directory
2. Jump to the **README.md** in the **tutorials** directory from the hyperlink in the SDK environment top directory
3. Jump to the **README.md** in the **3\_prepare\_model** directory from the hyperlink in the **README.md** in the **tutorials** directory
4. Jump to the **README.md** in the **develop\_on\_sdk** directory from the hyperlink in the **README.md** in the **3\_prepare\_model** directory
5. Jump to the **README.md** in the **2\_quantize\_model** directory from the hyperlink in the **README.md** in the **develop\_on\_sdk** directory
6. Jump to the **README.md** in the **image\_classification** directory from the hyperlink in the **README.md** in the **2\_quantize\_model** directory
7. Jump to each feature from each file in the **image\_classification** directory

## Prepare an AI model to quantize

1. Prepare an AI model (Keras) to quantize
  - Store the AI model (Keras) to be quantized in the SDK execution environment.

## Prepare images for quantization and evaluation

1. Prepare images used in training AI models because they will be used to calibrate the quantization
  - Store the directory containing the images, about 300 files, used in training the AI model in the SDK execution environment.
  - For example, if you want to use the *tutorials/\_common/dataset* directory, store it as follows:

```
tutorials/  
└─ _common  
   └─ dataset  
      │ training/ (1)  
      │ │ Image class name/  
      │ │ │ Image file  
      │ │ Image class name/  
      │ │ │ Image file  
      │ │ . . . .  
      └─
```

(1) Dataset used during training. This directory can have any subdirectory structure.

2. Create annotation data and label information file according to the [directory structure for ImageNet 1.0 format](#) for use as input during inference evaluation.

- Set up a directory for images to use for validation of the AI model. Store it in the SDK execution environment.
- For example, if you want to use the *tutorials/\_common/dataset* directory, store it as follows:

```
tutorials/  
└─ _common  
   └─ dataset  
      ├── validation/ (1)  
      │   ├── Image class name/  
      │   │   └─ Image file  
      │   ├── Image class name/  
      │   │   └─ Image file  
      │   └─ . . . .  
      └─ labels.json (2)
```

(1) Dataset used during evaluation. As described in the preceding create it according to the [directory structure for ImageNet 1.0 format](#).

(2) Label information file

- The format of label information files is a json file with the label name and its id value as follows:

```
{"daisy": 0, "dandelion": 1, "roses": 2, "sunflowers": 3, "tulips": 4}
```



See "Convert annotation information format" in the "CVAT Image Annotation Functional Specifications" for how to convert the format of annotation information to the preceding format when quantizing a user-prepared AI model.

## Create and edit the configuration file for quantization

1. Create and edit the configuration file, **configuration.json**, in the execution directory.



If you want to run image classification, the run directory becomes **quantize\_model/image\_classification**.



All parameters are required, unless otherwise indicated.



All values are case sensitive, unless otherwise indicated.



Do not use symbolic links to files and directories.

Configuration	Meaning	Range	Remarks
<b>source_keras_model</b>	Path to the AI model (Keras) to convert from. Specify a directory in Keras SavedModel format, or a file in h5 format.	Absolute path or relative to notebook (*.ipynb)	
<b>dataset_image_dir</b>	Directory containing dataset images for calibration during quantization	Absolute path or relative to notebook (*.ipynb)	
<b>batch_size</b>	Number of sets of images to be calibrated during quantization to find features such as weights and biases	1 or more and less than or equal to the total number of images contained in <b>dataset_image_dir</b>	
<b>input_tensor_size</b>	Size of the AI model input tensor (number of pixels on one side of image)	Comply with AI model input tensor	
<b>iteration_count</b>	Number of iterations when quantizing	1 or more	
<b>output_dir</b>	Directory to store the quantized AI model	Absolute path or relative to notebook (*.ipynb)	

Configuration	Meaning	Range	Remarks
<b>evaluate_image_dir</b>	Directory containing images to use as input during inference	Absolute path or relative to notebook (*.ipynb)	
<b>evaluate_image_extension</b>	Extension of image files to use as input during inference	String	
<b>evaluate_label_file</b>	Label information for AI models	Absolute path or relative to notebook (*.ipynb)	
<b>evaluate_result_dir</b>	Directory to store statistics of inference results	Absolute path or relative to notebook (*.ipynb)	

## Edit the notebook

1. Open the notebook for running quantization, *\*.ipynb*, in the execution directory.
2. Edit the preprocessing part of the notebook for calibration.
  - Edit the **FolderImageLoader** argument **preprocessing=[resize, normalization]** to set it equivalent to a preprocessing operation when training your AI model.

## Run quantization and evaluation

1. Open the notebook for running quantization, *\*.ipynb*, in the execution directory, and run the python scripts in it.

◦ The script does the following:

- Checks that *configuration.json* exists in the execution directory.
  - If an error occurs, the error description is displayed and running is interrupted.
- Checks that *configuration.json* includes values for **source\_keras\_model** and **dataset\_image\_dir**.
  - If an error occurs, the error description is displayed and running is interrupted.
- Reads the following values from *configuration.json*, makes the necessary settings in MCT, and then quantizes and converts the AI model (Keras):
  - *configuration.json* **source\_keras\_model**
  - *configuration.json* **dataset\_image\_dir**
  - *configuration.json* **batch\_size**
  - *configuration.json* **input\_tensor\_size**
  - *configuration.json* **iteration\_count**
- If an error occurs in external software, for example, MCT, the error output by the external software is displayed and running is interrupted.
- Outputs the AI model quantized by MCT (TFLite) **model\_quantized.tflite**, and the AI model converted to TFLite by standard TensorFlow functionality (TFLite) **model.tflite** to the directory specified in *configuration.json* **output\_dir**.
  - If the directory specified by **output\_dir** does not already exist, it is created at the same time.
- During conversion, the notebook will display information as follows (when **iteration\_count** is 10), for example:

```
0%|          | 0/10 [00:00<?, ?it/s]
...
30%|████      | 3/10 [00:15<00:35, 5.10s/it]
...
100%|██████████| 10/10 [00:50<00:00, 5.07s/it]
```

- Checks that *configuration.json* includes values for **output\_dir**, **evaluate\_image\_dir**, **evaluate\_label\_file**.
  - If an error occurs, the error description is displayed and running is interrupted.

- Reads the following values from `configuration.json`, makes the necessary settings for the tflite interpreter:
  - `configuration.json` `output_dir`
  - `configuration.json` `evaluate_image_dir`
  - `configuration.json` `evaluate_image_extension`
  - `configuration.json` `evaluate_labe_file`
  - `configuration.json` `evaluate_result_dir`
- Runs inference and displays statistics for three types of AI model: the original AI model (Keras), the AI model converted to TFLite by standard TensorFlow functionality (TFLite), and the AI model quantized by MCT (TFLite).
- Saves statistics as the file `results.json` in the directory specified in `evaluate_result_dir`.
- If an error occurs in external software, for example, TensorFlow, the error output by the external software is displayed and running is interrupted.
- While the AI model (TFLite) is being inferred, information is displayed as follows (when the number of images is 10), for example:

```

0%|          | 0/10 [00:00<?, ?it/s]
...
40%|████      | 4/10 [00:03<00:05, 1.08it/s]
...
100%|██████████| 10/10 [00:09<00:00, 1.08it/s]
```

- While the AI model (Kera) is being inferred, logs from TensorFlow library are displayed.
- While processing, you can interrupt with the Stop Cell Execution of notebook cell function.



## 7. Target performances/Impact on performances

- When the SDK environment is built, AI models (Keras) can be quantized and converted to AI models (TFLite) without any additional installation steps
- UI response time of 1.2 seconds or less
- If processing takes more than 5 seconds, then the display during processing can be updated sequentially

## 8. Assumption/Restriction

- None

## 9. Remarks

- To check the versions of Model Compression Toolkit (MCT) and TensorFlow
  - See *requirements.txt* in the SDK environment root directory.

## 10. Unconfirmed items

- None